

Userview Permission/ Form Permission Plugin

- Usages
- Abstract Class
 - [org.joget.apps.userview.model.UserviewPermission](#)
 - Method Detail
 - Abstract Methods
 - `isAuthorize`
 - Utility Methods
 - `getRequestParameters`
 - `setRequestParameters`
 - `getRequestParameter`
 - `getRequestParameterString`
 - `getCurrentUser`
 - `setCurrentUser`
 - Interface
 - [org.joget.apps.form.model.FormPermission](#)
- Plugin Properties Options
- Tutorials
- Related Community Plugins

Usages

- **Userview Permission Plugins** are used for handling permissions and access rights in a userview.
- **Form Permission Plugins** are used for handling permissions and access rights in a form and field element.
- A useable Userview Permission plugin must extends [org.joget.apps.userview.model.UserviewPermission](#) abstract class.
- A useable Form Permission plugin must extends [org.joget.apps.userview.model.UserviewPermission](#) abstract class and implements [org.joget.apps.form.model.FormPermission](#) interface.

Abstract Class

[org.joget.apps.userview.model.UserviewPermission](#)

- Under wflow-core module
- Extended [org.joget.plugin.base.ExtDefaultPlugin](#). Please refer to [Plugin Base Abstract Class and Interface](#).
- Implemented [org.joget.plugin.property.model.PropertyEditable](#). Please refer to [Plugin Base Abstract Class and Interface](#).
- A base abstract class to develop a Userview/Form Permission plugin.

Method Detail

Abstract Methods

`isAuthorize`
public abstract boolean isAuthorize()

Check the current user is authorized to proceed.

Utility Methods

`getRequestParameters`
public java.util.Map getRequestParameters()

```

Gets request parameters

setRequestParameters

public void setRequestParameters(java.util.Map requestParameters)

Sets request parameters

getRequestParameter

public java.lang.Object getRequestParameter(java.lang.String requestParameter)

Convenience method to get a parameter value

getRequestParameterString

public java.lang.String getRequestParameterString(java.lang.String requestParameter)

Convenience method to get a parameter String value.

Return Empty string instead of NULL.

getCurrentUser

public org.joget.directory.model.User getCurrentUser()

Gets current logged in user.

Return NULL if anonymous.

setCurrentUser

public void setCurrentUser(org.joget.directory.model.User currentUser)

Sets current logged in user.

```

Interface

org.joget.apps.form.model.FormPermission

- Under wflow-core module
- This interface is used to mark a Userview Permission Plugin is reusable in Form Builder.

- No interface method is available in this interface.

Plugin Properties Options

- Please refer to [Plugin Properties Options](#) for more information.

Tutorials

- [Guideline for Developing a Plugin](#)
- [How to develop a Not Permission](#)

Related Community Plugins

- **Bean Shell Permission**

org.joget.apps.userview.lib.BeanShellPermission (wflow-core)

- **Department Permission**

org.joget.apps.userview.lib.DepartmentPermission (wflow-core)

- **Group Permission**

org.joget.apps.userview.lib.GroupPermission (wflow-core)

- **Logged In User Permission**

org.joget.apps.userview.lib.LoggedInUserPermission (wflow-core)

- **Organization Permission**

org.joget.apps.userview.lib.OrganizationPermission (wflow-core)

- **User Permission**

org.joget.apps.userview.lib.UserPermission (wflow-core)