

General Settings

- User Interface Settings
- Timer Settings
- System Administration Settings

User Interface Settings

User Interface Settings	
Disable Front-End Admin Bar	<input type="checkbox"/>
Landing Page	<input type="text"/> <i>default: /home</i>
System Time Zone	<input type="text"/> <i>default: (SGST) Asia - Singapore</i>
System Locale	<input type="text"/> <i>default: en_US</i>
System Date Format	<input type="text"/> <i>default: dd-MM-yyyy hh:mm aa</i>
Using Locale Date Format	<input type="checkbox"/>
Enable User Locale Selection	<input type="checkbox"/>
User Locale Options (Language code, separated by comma ',')	<input type="text"/>
Display From Right To Left	<input type="checkbox"/>
CSS URL	<input type="text"/> <i>default: /w/css/new.css</i>
Custom CSS	<div style="border: 1px solid #ccc; height: 150px; width: 100%;"></div>
Disable HTML rendering in Datalist	<input type="checkbox"/>

Name	Description
------	-------------

Disable Front-End Admin Bar	Front-End Admin Bar allows the administrator to easily locate and manage elements created from the published Userview itself. You may turn it off permanently by checking on this option.
Landing Page	Change the default landing page apart from the App Center.
System Time Zone	By default, Joget will use server's timezone. You may override it with your own desired option.
System Locale	By default, Joget will use server's locale. You may override it with your own desired option. (Related: Manage Messages)
System Date Format	By default, Joget will use " dd-MM-yyyy hh:mm aa " as the date format. You may override it with your own desired option.
Using Locale Date Format	If checked, Joget will use the date format of the System Locale set above, overriding the System Date Format set above.
Enable User Locale Selection	Enables locale selection to users through User Profile.
User Locale Options (Language code, separated by comma ',')	Selection of locales available to users. (" Enable User Locale Selection " must be active first.)
Display From Right To Left	Enable RTL support.
CSS URL	Custom CSS file to replace the default look and feel of the web console. (Default CSS file resides at /jw/css/v3.css)
Custom CSS	Inline custom CSS to be appended into the web console in addition to the default/CSS URL.
Disable HTML rendering in Datalist	Determines if user defined HTML input value should be rendered in Datalist listing.

Timer Settings

Timer Settings	
Process Deadline Checker Interval (in seconds, 0 to disable)	<input type="text"/> <i>default: 0</i>

Name	Description
Process Deadline Checker Interval (in seconds, 0 to disable)	Interval checking in seconds for the Deadline elements. Disabled by default.

System Administration Settings

System Administration Settings

Master Login Username	<input type="text"/>
Master Login Password	<input type="password"/> <i>master login hash:-</i>
Uploaded File Storage Base Path	<input type="text"/> <i>default: D:\Docwflow</i>
Workflow Designer Base URL	<input type="text"/> <i>default: /jwdesigner</i>
Delete Process On Completion	<input type="checkbox"/>
Medium Warning Level	<input type="text"/> <i>default: 20</i>
Critical Warning Level	<input type="text"/> <i>default: 50</i>
File Upload Size Limit (MB)	<input type="text"/> <i>default: No Limit</i>
Disable Performance Analyzer	<input type="checkbox"/>
Performance Analyzer Threshold (ms)	<input type="text"/> <i>default: 100</i>
API Domain Whitelist (Separated by ";")	<input type="text"/>

Name	Description
Master Login Username	Master Login credential for API call. Please see JSON API Authentication .
Master Login Password	Master Login credential for API call. Please see JSON API Authentication .
Uploaded File Storage Base Path	System path to store uploaded users' files.
Workflow Designer Base URL	Workflow Designer Base URL. Defaulted to current Joget server path.
Delete Process On Completion	Delete process instance data on when process instance comes to an end.
Medium Warning Level	SLA indicator level. Please see Defining SLA Indicators . Default: 20.
Critical Warning Level	SLA indicator level. Please see Defining SLA Indicators . Default: 50.
File Upload Size Limit (MB)	File Upload Size Limit (MB) . Default: No Limit. <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p>The limit is applied on individual file.</p> <p>Example, if the value set here is 1 (1MB) then one may upload multiple files in a single form with total exceeding 1MB but individually, each file must not exceed 1MB.</p> </div>

Disable Performance Analyzer	Disable Performance Analyzer .
Performance Analyzer Threshold (ms)	Minimum threshold before showing the Performance Analyzer information.
API Domain Whitelist (Separated by ';')	Domain whitelist to allow API calls to Joget Workflow. <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"><p>Example "localhost;www.joget.org;dev.joget.org", or "*" to allow from everywhere (the behavior from previous releases).</p></div>