


XRPL Send Transaction Tool

- [Introduction](#)
- [Plugin Properties](#)
 - [Configure XRPL Send Transaction Tool](#)
 - [Transaction Details](#)
 - [Store Response To Workflow Variable](#)

Introduction

This [process tool](#) plugin allows you to send XRP from one wallet to another on the XRP ledger.


 Do ensure that the sender's wallet has sufficient balance for the amount to send & its required transaction fee.

Plugin Properties

Configure XRPL Send Transaction Tool

Name	Description
rippled Server	<p>Select the network to perform transactions on:</p> <ul style="list-style-type: none">• General Purpose Mainnet• Full History Mainnet• Devnet• Testnet• Custom Server <p>"Mainnet" uses real-world XRP. Please use "testnet" or "devnet" or your own test <i>rippled</i> server for testing purposes.</p> <p>The selectable networks here connects to official XRPL public servers. To learn more about all the network types and public servers available, see:</p> <ul style="list-style-type: none">• https://xrpl.org/public-servers.html• https://xrpl.org/parallel-networks.html
rippled URL	<p>Only available if Custom Server is selected for rippled Server property.</p> <p>If you have setup your own <i>rippled</i> server, key in its URL here.</p>

Transaction Details

Name	Description
Origin Wallet Address	Wallet classic address to send funds from. Hash Variable is also accepted.
Origin Wallet Seed Value	<p>This is the sender's wallet secret key required in order to perform actions with the sender's wallet.</p> <p>Only accepts Hash Variable that points to the sender's encrypted stored seed value.</p> <div> Caution Wallet seed MUST be strictly secured at all times, and only viewable to the intended user. Do NOT key in the plain-text seed value here. Anyone who possesses this seed has full unrestricted control and can do irreparable damage!</div>
Destination Wallet Address	Wallet classic address to send funds to. Hash Variable is also accepted.

Amount To Send (XRP)	Amount of XRP coin(s) to send. Amount can only contain max 6 decimal places. Hash Variable is also accepted.
----------------------	---

Store Response To Workflow Variable

Name	Description
Response Status	To indicate if this transaction is successful and validated.
Transaction Explorer URL	To store an auto-generated URL to see transaction details on the official XRPL explorer.